

APS VIDEO PLAYER

PROJECT DETAILS

Name	Software Release Notes
Doc. Status	Released
Author / Owner	Peter Heyer
Dokument ID	n/a

DATE	EDITED BY	DESCRIPTION
22.08.2019	Peter Heyer	Initial

246 **HELLA Aglaia Mobile Vision GmbH**
247 A member of the HELLA group
248 Ullsteinstraße 140
249 12109 Berlin / Germany
250
251 phone +49 (0) 30 2000 429-625
252 fax +49 (0) 30 2000 429-149
253 mail info@people-sensing.com
254 www.people-sensing.com
255
256 Deutsche Bank AG
257 IBAN: DE 07 4167 0027 0609 8420 00
258 BIC SWIFT: DEUTDE33416
259 AG Berlin-Charlottenburg
260 HRB 66976 B
261 VAT-ID No.: DE 194710861
262 EORI No.: DE 5106826
263 Managing Director: Kay Talmi

TABLE OF CONTENTS

1	General Information.....	3
2	New Features.....	3
3	Changed Features.....	3
4	Removed Features.....	3
5	Corrected Errors.....	4
6	Known issues, restrictions and notes.....	4
7	Tool Compatibility.....	4
8	Reference Documents.....	4
9	Contact.....	4

File Name	Author / Owner	Dokument ID	Date	Page
Release-Notes-APSVideoPlayer-1.11.0-en.docx	Peter Heyer	n/a	22.08.2019	2 / 4

1 GENERAL INFORMATION

Operating System	Windows 7, 8, 10 (64-bit versions)
Firmware version:	1.11.0
Available starting from:	2019-08-20
Released by:	Hella Aglaia GmbH Ullsteinstrasse 140 12109 Berlin Germany people.counter.support@hella.com www.people-sensing.com

2 NEW FEATURES

No.	Description
1	Possibility to play videos of multi sensor arrays. The player will show moving tracks on a stiched image.
2	Visualization of new Stop/Motion Detector in APS-MSW v1.9
3	Adaption for new extended height range in APS-RS SW v1.16

3 CHANGED FEATURES

No.	Description
1	The track info window now shows the dwell time of tracks as "dwell" in seconds instead of "age" in frames.

4 REMOVED FEATURES

No.	Description
1	None

File Name	Author / Owner	Dokument ID	Date	Page
Release-Notes-APSVideoPlayer-1.11.0-en.docx	Peter Heyer	n/a	22.08.2019	3 / 4

5 CORRECTED ERRORS

No.	Description
1	In Videos recorded with APS-RS SW before 1.8 the fill level of monitored zonens is constantly 0

6 KNOWN ISSUES, RESTRICTIONS AND NOTES

No.	Description
1	In APS-M videos the range overlay (read area) may not be displayed correctly on sensors installed with a high pitch angle.

7 TOOL COMPATIBILITY

The APS people sensor software will be continuously improved, and new features will be added. Thus the video player needs to be extended sometimes as well. However, we strive to keep the program backwards compatible to videos recorded with every older firmware version.

VIDEO PLAYER	APS-M FIRMWARE	APS-RS FIRMWARE
1.6.0	all versions until 1.2	all versions until 1.8
1.7.0	all versions until 1.4.1	all versions until 1.12
1.8.0	all versions until 1.5	all versions until 1.12
1.10.0	all versions until 1.8	all versions until 1.15
1.11.0	all current versions (at least until 1.9)	all current versions (at least until 1.16)

8 REFERENCE DOCUMENTS

No.	Title	Date
1	APS-SW-Manual-Video-Player-1.11.0-en.pdf	08.2019

9 CONTACT

Questions and support requests can be sent by e-mail to:

people.counter.support@hella.com

File Name	Author / Owner	Dokument ID	Date	Page
Release-Notes-APSVideoPlayer-1.11.0-en.docx	Peter Heyer	n/a	22.08.2019	4 / 4

Vertraulich. Weitergabe sowie Verwendung und Mitteilung ist nur mit unserer ausdrücklichen Genehmigung gestattet. Alle Rechte vorbehalten.
This document is confidential. Its contents are not to be exploited, passed on or disclosed to third parties without our express permission. All rights are reserved